


Ensemble Jobs for Better Throughput

Paul Rich
Ray Loy



Argonne **Leadership**
Computing Facility

This information only applies to
ALCF Blue Gene/Q resources.

Use on other types of systems or at other sites
will likely require significant adjustments.

Overview


- ⦿ Definitions
- ⦿ Picking the right type of job
- ⦿ Basic Script mode jobs
- ⦿ Ensemble jobs
 - ⦿ Sub-block runjobs
 - ⦿ Multi-block jobs
 - ⦿ Hybrid multi-block + sub-block jobs
- ⦿ Error checking in job scripts

Definitions and Disambiguation

- ⊙ Block - A Blue Gene partition
- ⊙ Cobalt Job - A job submitted to Cobalt via qsub. Shows up in qstat.
 - ⊙ Non-script job
 - ⊙ Script Job - A Cobalt job submitted with the *--mode script* option
 - Can do many things a non-script job can't
- ⊙ Blue Gene job - A task run on the compute nodes via runjob
 - ⊙ runjob is BG equivalent of mpirun or mpiexec
- ⊙ Ensemble job - A Cobalt job with >1 simultaneous runjob
- ⊙ Sub-block runjob - Runjob only uses part of a booted block. The block can be shared with other sub-block runjobs
- ⊙ Multi-block job - A Cobalt job that takes the overall block assigned by the scheduler and separately boots smaller blocks within it. Simultaneous runjobs may be run on these smaller blocks.


Examples of multi-block and sub-block jobs

Multi-block job (one runjob per block)




4K

Sub-block runjobs



512 nodes




Minimum partition size on Mira

For jobs with the same characteristics: higher job size = faster score increase

Types of script jobs and the best tool for the job

- ⦿ Basic Script Jobs
 - ⦿ Can run commands both before and after the runjob
 - ⦿ Can run a series of runjobs one after the other
- ⦿ Ensemble Jobs
 - ⦿ You want to run multiple simultaneous tasks
 - ⦿ Single-block with sub-block runjobs
 - All tasks are smaller than the smallest block size on the system
 - Mira=512, Cetus=128, Vesta=32
 - ⦿ Multi-block
 - Boot smaller blocks within the overall Cobalt allocation
 - Two possibilities
 - Run one runjob on each block
 - OR run multiple sub-block runjobs in each block
 - ⦿ Advanced: Either sub-block or multi-block can change runjob size between tasks
 - ⦿ NOTE: None of these methods are MPMD runs

Choosing the Right Type of Submission



Equivalent Cobalt jobs

- ⦿ Non-script

- ⦿ `qsub -t 10 -n 32 --mode c16 --proccount 512 a.out arg1 arg2`

- ⦿ Script

- ⦿ `qsub -t 10 -n 32 --mode script job.sh`

- `#!/bin/bash`

- `runjob -p 16 -np 512 --block $COBALT_PARTNAME : a.out arg1 arg2`

- ⦿ `qsub job.sh`

- `#!/bin/bash`

- `#COBALT -t 10 -n 32`

- `runjob -p 16 -np 512 --block $COBALT_PARTNAME : a.out arg1 arg2`

- ⦿ `qsub job.sh`

- `#!/bin/bash`

- `#COBALT -t 10 -n 32 --disable_preboot`

- `boot-block --block $COBALT_PARTNAME`

- `runjob -p 16 -np 512 --block $COBALT_PARTNAME : a.out arg1 arg2`

Script job basics

- ⊙ Script can be any executable for a *front-end node* (e.g. shellscript, python, ...) if you submit with `--mode script`
 - ⊙ Shell scripts containing `#COBALT` are implicitly script mode
- ⊙ The job script runs on a front-end node but the set of allocated compute nodes is charged for the entire runtime.
 - ⊙ Avoid running long serial (non-runjob) commands e.g. compilation
- ⊙ By default, the entire block allocated by Cobalt will be booted before starting the script
- ⊙ Cobalt sets: `$COBALT_JOBID`, `$COBALT_PARTNAME`, `$COBALT_PARTSIZE`, ...
- ⊙ `runjob` starts execution on compute nodes
 - ⊙ Multiple runjobs may be run in series
 - Advanced: check status of block in between runjobs
- ⊙ Be careful about last command in a script
 - ⊙ “echo done” will cause exit status of 0 regardless of anything else!
 - ⊙ Very important if you’re using job dependencies
- ⊙ The Cobalt job's `.output/.error` are the `stdout/stderr` from your job script.
 - ⊙ Do not delete these files (or the `.cobaltlog`) - help us help you

Consecutive runjobs

```
#!/bin/bash
#COBALT -t 10 -n 32

runjob -p 16 --np 512 --block $COBALT_PARTNAME : a.out arg1 arg2
status=$?

if [ $status -ne 0 ] ; then
    echo "Error on first run, quitting"; exit 1
fi

runjob -p 8 --np 256 --block $COBALT_PARTNAME : a.out foo bar
status=$?

if [ $status -ne 0 ] ; then
    echo "Error on second run"
fi
exit $status
```

Sub-block runjobs

- ⊙ Sub-block runjobs may be used within any script job
 - ⊙ e.g. a simple one-block job, or a multi-block job
- ⊙ Recommended use is only within smallest hardware partition
 - ⊙ Mira=512, Cetus=128, Vesta=32
 - ⊙ Can run down to the single-node level
 - ⊙ Only supported for booted blocks of 512 nodes or smaller
- ⊙ Use `runjob --corner` and `--shape` flags
 - ⊙ Shape gives the extents of a 5D patch e.g. "2x2x4x2x2" (=64 nodes)
 - *man runjob* has a list of common shapes for small sub-block sizes
 - Size must be a power of 2
 - ⊙ Corner is a hardware location
 - A disjoint set of corners may be obtained by passing the block name and a shape to `/soft/cobalt/bgq_hardware_mapper/get-corners.py`

Sub-block runjob example

```
#!/bin/bash
```

```
#COBALT -n 32 -t 10
```

```
SHAPE=1x2x2x2x2 # 16 nodes
```

```
CORNERS=`get-corners.py $COBALT_PARTNAME $SHAPE`
```

```
for C in CORNERS; do
```

```
    runjob --block $COBALT_PARTNAME --corner $C --shape $SHAPE -p 1 --np 16  
: a.out >RUNJOB.$C.output 2>&1 &
```

```
    sleep 3
```

```
done
```

```
wait
```

```
exit 0 # Need to do more coding to collect runjob statuses
```

Sub-block runjob Caveats

- ⊙ If a sub-block runjob exits abnormally, the block it was in may go into an error state
 - ⊙ May not kill other current sub-block runjobs
 - Other jobs only stay up if a software failure
 - ⊙ However, will prevent future jobs from starting
 - ⊙ When this happens, wait for sub-block runjobs to complete (or kill them), then reboot block.
- ⊙ Avoid
 - ⊙ Starting runjobs too quickly
 - Must use a "sleep 3" after starting each one in background
 - ⊙ Overloading I/O nodes
 - ⊙ Too many runjobs in total
 - Each runjob uses non-scalable resources that stress the system
 - Maximum of 512 runjobs in *all* your running jobs

Multi-block Jobs

- ⊙ The Cobalt job's allocated block either must start off unbooted or be freed at the start of the job
 - ⊙ `qsub` option (or `#COBALT`) `--disable_preboot`
- ⊙ Boot smaller “child” blocks of the main allocated block
 - ⊙ Cannot be smaller than the smallest bootable partition
 - ⊙ May be subject to torus wiring restrictions
- ⊙ `get-bootable-blocks` will return all child blocks currently available to boot in a main block
 - ⊙ Can constrain to particular sizes and geometries
 - ⊙ Booting one child may block others, they will no longer be available
- ⊙ `boot-block` can boot, free, or reboot a partition
 - ⊙ After booting or rebooting, the block is ready for use
 - ⊙ nonzero exit status means a problem occurred
- ⊙ Runjob works in the normal way, just using one child block per invocation
 - ⊙ Advanced: you can also run a set of sub-block runjobs on each child

Example Multi-block Script

```
#!/bin/bash
#COBALT -n 1024 -t 10 --disable_preboot

BLOCKS=`get-bootable-blocks --size 512 $COBALT_PARTNAME`

for BLOCK in $BLOCKS ; do
    boot-block --block $BLOCK &
done
wait

for BLOCK in $BLOCKS ; do
    runjob --block $BLOCK : ./my_binary >RUNJOB.$BLOCK 2>&1 &
    sleep 3 # Important
done
wait

# More code required to check for runjob success/fail
exit 0
```

Based on <http://trac.mcs.anl.gov/projects/cobalt/wiki/BGQUserComputeBlockControl>

Multi-block Caveats

- ⊙ Some block sizes may have issues running next to each other
 - ⊙ Adjacent 4096- and 1024-node full-torus blocks (due to physical wiring)
 - Use partial mesh versions of these blocks
 - ⊙ Incremental approach: after booting one block, repeat call to get-bootable-blocks
- ⊙ Booting a block may fail
 - ⊙ File systems may fail to mount. Hardware may die during boot.
 - ⊙ boot-block will automatically re-try 3 times before giving up
 - ⊙ partlist will show an error as blocked(SoftwareFailure)
 - Software errors can be cleared by rebooting
- ⊙ Can mix block sizes and change sizes
 - ⊙ To change, free children then boot a new set
 - ⊙ *If using persistent CNK ramdisk (/dev/persist), contents will be erased by a block reboot.*
- ⊙ Once a block is booted, can run multiple runjobs on it
- ⊙ Some blocks share I/O resources
 - ⊙ check ALCF system documentation
- ⊙ Test your script on Cetus, if possible
 - ⊙ Adjust block sizes for test

Considerations for Mira

- ⦿ Adjacent 1024 node and 4096 node blocks have potential torus wiring conflicts
 - ⦿ Avoid by using blocks with partial mesh dimensions
 - ⦿ 1024: MIR-XXXXX-YYYYY-1-1024 (same blocks used for the prod-short/prod-long queues)
 - ⦿ 4096: MIR-XXXXX-YYYYY-2-4096 (Not in any normal queues)
- ⦿ Certain other size blocks may have alternate shapes defined
 - ⦿ You may have to use grep to filter the output of get-bootable-blocks
- ⦿ If using mesh blocks to pack, **all** blocks of that size must be mesh
 - ⦿ Cannot mix torus and mesh due to wiring
- ⦿ When packing different sizes, start with largest block and work down in sizes
 - ⦿ This will result in the most efficient packing
- ⦿ No more than 512 simultaneous runjob invocations
 - ⦿ More in series is fine, this is a limit for simultaneous runs
 - ⦿ This is based on a global Blue Gene control system limit

Hybrid Multi-block boot + Sub-block runjobs

```
#!/bin/bash
#COBALT -n 1024 -t 10 --disable_preboot

SHAPE=2x2x2x2x2 # 32 nodes
BLOCKS=`get-bootable-blocks --size 512 $COBALT_PARTNAME`

for B in $BLOCKS ; do
    boot-block --block $B &
done
wait

for B in $BLOCKS ; do
    CORNERS=`get-corners.py $COBALT_PARTNAME $SHAPE`
    for C in CORNERS; do
        runjob --block $B --corner $C --shape $SHAPE -p 1 -np 32 : a.out >LOG.$B.$C.output 2>&1 &
        sleep 3
    done
done
wait

# More code required to check for runjob success/fail
exit 0
```

Handling Errors

- ⦿ Check Exit Statuses
 - ⦿ Non-zero means something went wrong
 - ⦿ Check boot-block, runjob
- ⦿ Blocks may encounter errors that cause a boot to fail but are recoverable.
 - ⦿ Try to boot the block again
 - ⦿ Recommend no more than 3 retries. At that point there is likely a hardware problem
 - ⦿ Contact support@alcf.anl.gov if you see problems booting a particular block
- ⦿ If runjob exits with a nonzero status the block may have had a “software failure”
 - ⦿ Check partlist for the block, if the status is “hardware offline (SoftwareFailure)” you can reboot the block to clear the error.
 - `boot-block --reboot $BLOCK_NAME`
 - ⦿ If the block states "hardware offline" with a different error, the block is not recoverable due to an actual hardware failure.

Useful Places to Look

- ⦿ Example scripts may be found on ALCF systems at:
 - ⦿ /soft/cobalt/examples
- ⦿ Cobalt Manpages may be found on all ALCF systems and on:
 - ⦿ <https://trac.mcs.anl.gov/projects/cobalt/wiki/CommandReference>
- ⦿ Advanced Bash Scripting reference:
 - ⦿ <http://www.tldp.org/LDP/abs/html/>

Questions?

Partition dimensions on BG/Q systems

Cetus

Nodes	A	B	C	D	E
128	2	2	4	4	2
256	4	2	4	4	2
512	4	4	4	4	2
1024	4	4	4	8	2
2048	4/8	4	4/8	4/8	2

Vesta

Nodes	A	B	C	D	E
32	2	2	2	2	2
64	2	2	4	2	2
128	2	2	4	4	2
256	4	2	4	4	2
512	4	4	4	4	2
1024	4	4	4/8	8/4	2
2048	4	4	8	8	2

Mira

Nodes	A	B	C	D	E
512	4	4	4	4	2
1024	4	4	4	8	2
2048	4	4	4	16	2
4096	4/8	4	8/4	16	2
8192	4	4	16	16	2
12288	8	4	12	16	2
16384	4/8	8/4	16	16	2
24576	4	12	16	16	2
32768	8	8	16	16	2
49152	8	12	16	16	2

Command: **partlist**

<http://www.alcf.anl.gov/user-guides/machine-partitions>

Minimum partition sizes on BG/Q machines

Mira
48 racks

512 nodes = minimum partition size on Mira

	R00	R01	R02	R03	R04	R05	R06	R07	R08	R09	R0A	R0B	R0C	R0D	R0E	R0F
M1	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid
M0	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid

	R10	R11	R12	R13	R14	R15	R16	R17	R18	R19	R1A	R1B	R1C	R1D	R1E	R1F
M1	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid
M0	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid

	R20	R21	R22	R23	R24	R25	R26	R27	R28	R29	R2A	R2B	R2C	R2D	R2E	R2F
M1	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid
M0	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid

Cetus
4 racks

128 nodes = minimum partition size on Cetus

	R00	R01	R02	R03
M1	2x2 grid	2x2 grid	2x2 grid	2x2 grid
M0	2x2 grid	2x2 grid	2x2 grid	2x2 grid

Vesta
2 racks

32 nodes = minimum partition size on Vesta

	R00				R01			
M1	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid
M0	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid	2x2 grid

Error checking - background processes

```
# a handy bash function
```

```
. /soft/cobalt/examples/ensemble/script/wait-all
```

```
pids=""
```

```
for B in $BLOCKS ; do
```

```
  boot-block -block $B &
```

```
  pids+=" $!"
```

```
done
```

```
wait-all "boot" $pids
```

```
[ $? -ne 0 ] && exit 1
```

```
# bash function from above
```

```
# quit if any of the boots fail
```

```
# Can use the same method for any backgrounded commands
```

```
# E.g. runjob
```


Example: array of runjob args

```
rootdir=`pwd`
```

```
dir[0]=$rootdir/subdir_a
```

```
dir[1]=$rootdir/subdir_b
```

```
...
```

```
cmd[0]="-p 1 --np 16 : a.out"
```

```
cmd[1]="-p 16 --np 256 : b.out"
```

```
...
```

```
i=0
```

```
for B in $BLOCKS ; do
```

```
  cd ${dir[$i]}
```

```
  runjob --block $B ${cmd[$i]} >LOG.output 2>LOG.error &
```

```
  sleep 3
```

```
  ((i++))
```

```
done
```

```
wait
```

Advanced: Block Translation

- ⊙ `/soft/cobalt/bgq_hardware_mapper` contains basic helper scripts
- ⊙ `hardware2coord` -- take a hardware location and translate to ABCDE
- ⊙ `coord2hardware` -- take an ABCDE location and translate to a hardware location
- ⊙ `get-corners.py` experimental -- given a block name and a shape, generate every valid `--corner` argument for that shape on that block.
 - ⊙ Must be used on a block of 512 nodes or smaller